



WARNING !

A execution or installation problem of Circe may be due to management writing rights on the system partition (C :), which evolves according to the versions and updates of Windows.

Two solutions can be envisaged:

- 1) Ask your IT manager to grant you administrator privileges, then run Circe so that it can create the files it needs to run (conversion grids in binary format).
- 2) Install Circe in your personal folder (C:\Users\{username}\Documents). However, this solution will lead to an error message each time you close the program, indicating that it can not save its state (projection, reference system, mode used during the session). The only consequence of this error is that the software will display the default settings at each opening.